

FIG.1




FIG.2





FIG.3



## FIG.4

### ;SCENARIO TEMPLATE FOR PRINTER INSTALLATION

[Install.RICOH Port Monitor]

ComponentName= RICOH Port Monitor

ComponentKind=Application

Setup=..¥NETWORK¥RICOH¥PORTMON¥DISK1¥SETUP.EXE

[Install.@DRIVERNAME@]

ComponentName=@DRIVERNAME@

ComponentKind=PrinterDriver

Language=JAPANESE

Setup=..¥DRIVERS¥SETUP.EXE

DefaultDriver=

InitializeFile=@INI@

[Port.@ADDRESS@]

Monitor=RICOH Port Monitor

PortName=@ADDRESS@

PortAddress=@ADDRESS@

[PrinterObject.@PNAME@]

PrinterName=@PNAME@

DriverName=@DRIVERNAME@

Comment=

SetDefault=ON

PortSectionName=Port.@ADDRESS@

UserID=@UID@

InitializeFile=@INI@

Shared=OFF

ShareName

## FIG.5

;SCENARIO TEMPLATE FOR PRINTER INSTALLATION OF  
SALES SECTION No.1

[Install.RICOH Port Monitor]

ComponentName= RICOH Port Monitor

ComponentKind=Application

Setup=..¥NETWORK¥RICOH¥PORTMON¥DISK1¥SETUP.EXE

[Install.R-DriverA]

ComponentName=R-DriverA

ComponentKind=PrinterDriver

Language=JAPANESE

Setup=..¥DRIVERS¥SETUP.EXE

DefaultDriver=

InitializeFile=eigyo1.ini

[Port.127.0.0.1]

Monitor=RICOH Port Monitor

PortName=127.0.0.1

PortAddress=127.0.0.1

[PrinterObject Sales Section No.1]

PrinterName Sales Section No.1

DriverName R-DriverA

Comment=

SetDefault=ON

PortSectionName=Port127.0.0.1

UserID=

InitializeFile=eigyo1.ini

Shared=OFF

ShareName

## FIG.6

;SCENARIO TEMPLATE FOR PRINTER INSTALLATION OF  
SALES SECTION No.2

[Install.RICOH Port Monitor]

ComponentName= RICOH Port Monitor

ComponentKind=Application

Setup=..¥NETWORK¥RICOH¥PORTMON¥DISK1¥SETUP.EXE

[Install.R-DriverB]

ComponentName=R-DriverB

ComponentKind=PrinterDriver

Language=JAPANESE

Setup=..¥DRIVERS¥SETUP.EXE

DefaultDriver=

InitializeFile=eigyo2.ini

[Port.127.0.0.1]

Monitor=RICOH Port Monitor

PortName=127.0.0.1

PortAddress=127.0.0.1

[PrinterObject Sales Section No.2]

PrinterName Sales Section No.2

DriverName R-DriverB

Comment=

SetDefault=ON

PortSectionName=Port127.0.0.1

UserID=

InitializeFile=eigyo2.ini

Shared=OFF

ShareName

FIG. 7




FIG.8






FIG.9

HOST NAME	USER ID @UID@	IP ADDRESS @ADDRESS@	PRINTER NAME @PNAME@	PRINTER DRIVER NAME @DRIVERNAME@	INITIALIZATION FILE @INI@
host1-1	10	127.0.0.1	Sales Section No.1	R-Driver A	eigyo1.ini
host1-2	20	127.0.0.1	Sales Section No.1	R-Driver A	eigyo1.ini
host1-3	30	127.0.0.1	Sales Section No.1	R-Driver A	eigyo1.ini
host1-4	40	127.0.1.1	Sales Section No.2	R-Driver B	eigyo2.ini
host1-5	50	127.0.1.1	Sales Section No.2	R-Driver B	eigyo2.ini
host1-6	60	127.0.1.1	Sales Section No.2	R-Driver B	eigyo2.ini

FIG.10

LOG-IN NAME	USER ID @UID@	IP ADDRESS @ADDRESS@	PRINTER NAME @PNAME@	PRINTER DRIVER NAME @DRIVERNAME@	INITIALIZATION FILE @INI@
satoh	10	127.0.0.1	Sales Section No.1	R-Driver A	eigyo1.ini
suzuki	20	127.0.0.1	Sales Section No.1	R-Driver A	eigyo1.ini
tanaka	30	127.0.0.1	Sales Section No.1	R-Driver A	eigyo1.ini
hayashi	40	127.0.1.1	Sales Section No.2	R-Driver B	eigyo2.ini
ogawa	50	127.0.1.1	Sales Section No.2	R-Driver B	eigyo2.ini
saitoh	60	127.0.1.1	Sales Section No.2	R-Driver B	eigyo2.ini